



# Instructions for the AirPods Pro Beta

Important: Once installed on your AirPods Pro, the beta software cannot be removed. Your unit will continue to run this software until an updated nonbeta version of the software is released. In the meantime, you'll automatically receive any additional beta software updates as long as you've enabled your AirPods Pro to receive them using the steps below.

## Prerequisites:

- An iPhone running [iOS 15 beta](#) software
- A Mac running [Xcode 13 beta](#) software
- A set of AirPods Pro (fully charged)

## Step 1 - Install the AirPods Pro Seed (2021) profile on your iPhone.

- a. Download the [iOSAirPodsProSeed.mobileconfig configuration profile](#).
- b. On your iOS device: Download the configuration profile, then follow the installation instructions.

Or, on your Mac or PC: Save the file to your hard disk, then email it to an account on your iPhone. Tap the configuration profile in Mail and follow the installation instructions.

## Step 2 - Pair your AirPods Pro with your iPhone.

- a. Verify that your AirPods Pro are [connected to your iPhone](#).

## Step 3 - Enable your AirPods Pro to receive beta software.

- a. Connect your iPhone to your Mac.
- b. Launch Xcode 13 beta on your Mac.
- c. On your iPhone, go to Settings > Developer, then choose Prerelease Beta Firmware.
- d. Find your AirPods Pro in the list of paired devices, then tap to turn on automatic beta software updates.
- e. Read and follow the onscreen instructions for receiving beta software updates. Please be patient; it can take up to 24 hours to receive and install these updates.

**Reporting issues**

Use [Feedback Assistant](#) to report any issues you encounter with AirPods Pro beta software.

**Turning off beta software updates**

If you no longer wish to receive beta software updates for your AirPods Pro, repeat the instructions in step 3 to turn them off. Although your AirPods Pro won't receive any new beta software updates, they will remain on the installed beta software until the next release of nonbeta software is available.